TS 704 ID CARD MANUALS

- 1. OPEN TS704 TEMPLATE ON COREL DRAW,
- 2. GO TO PRINT AND

3. SELECT TS700 SERIES FROM THE LIST OF AVAILABLE PRINTERS

Caractel					
General	Color	Composite Layout Prepress	IØ No Issues		
Desti	nation			na	
Pri <u>n</u> t	ter:	Canon TS700 series (Copy 6)	×	Preferences	
Page	e:	Use printer default (Portrait)	~	Use PPD	
Statu	us:	Default printer; Ready			
Loca	ation:	USB064			
Com	nment:			Print to file	
Print	range		Copies		
() (urrent do	ocument O Documents	Number of <u>c</u> opies:	1	
00	- urrent pa	age OSelection		Lake I	
0.		1	1 2 3 3	Collate	
CLE	ages:	1		1	
		Even & Odd 🛛 🗠	Print as <u>b</u> itmap:	300 🗘 dpi	
Print st	tyle:	Custom (Current settings not save	ed) 🔻	Sa <u>v</u> e As	
D .3				A	
Pri	nt Previej	<u>w</u>	UN Cancel	нер	

4. GO TO PREFERENCES AND SELECT THE FOLLOWING

MEDIA TYPE = OTHER PAPERS – PRINTABLE DISC

PRINTER PAPER SIZE = MULTIPURPOSE TRAY

PAPER SOURCE = MULTIPURPOSE TRAY

lick Setun	Main	Dago	Cature	Maintonanac						
uick Setup	Main	Fage 3	setup	Maintenance						
Commonly	Used <u>S</u> e	ettings								
🗾 Stan	dard							^		
Phot Phot	o Printin	g								
Busir	ness Do	cument						-		
Pape	er Saving	9						~		
L. I LOUG					1		-	_		
					S	ave	Delete	÷.		before printing
										E berore printing
Additional I	-eatures									
TTT m		2								
Duplex	Printing									
Duplex	Printing less Prin	ting								
Duplex	Printing less Prin ale Print	ting								
Duplex	Printing less Prin ale Print	ting								
Duplex Borderl Graysc Draft Media Type	Printing less Prin ale Print	ting				Print <u>e</u> r P	aper Size:			
Duplex Duplex Borderi Graysc Draft Media Type Printable di	Printing less Prin ale Print	ting			~	Printer P. Multi-pu	aper Size: rpose Tray	,		~
Duplex Duplex Graysc Draft Media Type Printable di	Printing less Prin ale Print	ing			~	Print <u>e</u> r P. Multi-pu Orien	aper Size: pose Tray tation:	(lortrait C) Landscape
Duplex Duplex Dorder Graysc Draft Media Type Printable di Print Quality	Printing less Prin ale Print	ing			~	Print <u>e</u> r P. Multi-pu <u>O</u> rien Paper So	aper Size: pose Traj tation: burce:	<u>/</u> @Р	'ortrait C) Landscape
Duplex Duplex Dordert Graysc Draft Media Type Printable di Print Quality High	Printing less Prin ale Print	ing			*	Print <u>e</u> r P. Multi-pu <u>O</u> rien Pape <u>r</u> So Multi-pu	aper Size: rpose Tray tation: purce: rpose Tray	/ @P	'ortrait C) Landscape
Duplex Duplex Dordert Graysc Draft Media Type Printable di Print Quality High	Printing less Print ale Print	ing			~ ~	Print <u>e</u> r P. Multi-pu Orien Pape <u>r</u> Sc Multi-pu	aper Size: rpose Traj tation: purce: rpose Traj	('ortrait C) Landscape
Duplex Duplex Graysc Graysc Draft Media Type Printable di Print Quality High	Printing less Prin ale Print	ting			~ ~	Printer P. Multi-pu Orien Paper Sc Multi-pu <u>C</u> opies:	aper Size: rpose Traj tation: purce: rpose Traj	/ () () () () () () () () () ()	°ortrait ⊂) Landscape 99)
Duplex Duplex Dorderi Graysc Draft Media Type Printable di Print Quality High Always I	Printing less Print ale Print : sc	ing	Settin	75	>	Printer P. Multi-pu Qrien Paper Sc Multi-pu <u>C</u> opies:	aper Size: rpose Tray tation: pource: rpose Tray	() () () () () () () () () () () () () (fortrait C) Landscape 99)

5. CLICK OK, APPLY THEN PRINT PREVIEW



7. FOLLOW THE SCREEN INSTRUCTION AND,

8. PUSH IN THE OUTPUT TRAY, INSERT THE ID CARD TRAY AND PRESS OK BUTTON ON THE PRINTER.

